

Shortcut Keys

Click anywhere in the Viewer to bring the window to front and to enable the following keyboard shortcuts:

Down Arrow	Select next file.
Shift-Down Arrow	Select next folder.
Up Arrow	Select previous file.
Shift-Up Arrow	Select previous folder.
Left Arrow	Scroll back 1/10th screen width.
Right Arrow	Scroll forward 1/10th screen width.
Shift-Left Arrow	Scroll back one screen width.
Shift-Right Arrow	Scroll forward one screen width.
Space Bar	Play selection.
R	Reload file.
0	Accept Auto ID label.
1-8	Select the corresponding ID label on the top row of customizable buttons in the Metadata Panel.
+ or Z	Zoom in X axis.
- or Z	Zoom out X axis.
=	Zoom to fit X axis.
.	Toggle the zero-crossing dots display.
/	Toggle the compressed/expanded view.

Pre-set zoom levels can be triggered via keyboard shortcuts.

Control-Z followed by a number key 1,2,3,4,5,6,7,8,9, or 0 to activate a zoom level pre-set. This will set the X and Y zoom levels of the spectrogram as well as the Y axis starting frequency to one of 10 pre-sets.

Shift-Control-Z followed by a number key to set a pre-set to the current zoom level. For example, you can set your desired zoom and then do this to save the zoom level.

Control-Z Control-Z followed by a number key to go back to the default preset value and zoom to that default zoom level.

Zoom levels are separate for bat mode and bird mode.

For non-bat mode, default Y axis is 0-12kHz; for bat mode, default Y axis is 0-128kHz.

Default X zooms are as follows (non-bat, bat, for width of spectrogram):

No.	Non-bat	Bat
1	500ms	50ms
2	1s	100ms
3	2s	200ms
4	4s	400ms
5	8s	800ms (This is the default zoom level on first launch)
6	16s	1.6s
7	32s	3.2s
8	1m 4s	6.4s
9	2m 8s	12.8s
0	4m 16s	25.6s